

Important License Activation Information

When you purchase a TickStack application, your license requires manual activation, which may take up to 24 hours. Once activated, you'll receive an email from support@tickstack.io containing login credentials for your user dashboard where you can manage your licenses. Please note that you cannot use the product until you receive this activation email.

VPS Requirements for Optimal Performance

Why Use a VPS?

For 100% reliable operation of this EA, we strongly recommend using a Virtual Private Server (VPS). Your home computer may experience internet outages, power failures, or require restarts that can interrupt trading operations.

VPS Requirements Checklist

When selecting a VPS provider, ensure they meet these essential requirements:

- Guaranteed 100% uptime (or 99.9%+ SLA)
 - DLL support enabled - Many VPS providers block DLL execution for security
 - Windows Server environment with MetaTrader 5 compatibility
 - Low latency connection to your broker's servers
- 24/7 technical support

Our Recommended VPS Provider

We use and recommend FXVM for all our trading operations. They guarantee:

- 100% uptime SLA
- Full DLL support for MetaTrader EAs
- Optimized servers for forex trading
- Excellent customer support

Special Offer for TickStack Users

Get started with our trusted VPS partner:

 <https://fxvm.net/?aff=27129>

Bonus: When you sign up through our affiliate link, you'll receive a 10% discount on your next purchase of any TickStack product!

Important Notes


- Always verify with your VPS provider that DLL calls are permitted
- Test your EA on the VPS environment before going live
- Ensure your VPS has adequate resources (minimum 2GB RAM recommended)

TickStack Metatrader Application Installation Guide:




Step 1: Install License Validator Files

- Copy both "LicenseValidator_x64.dll" and "LicenseValidator_x86.dll" into your MT5 Libraries folder
- To locate the Libraries folder:
 1. Open your Metatrader terminal
 2. Click "File" → "Open Data Folder" in the top left corner
 3. Navigate to "MQL5" → "Libraries"

Note: If you own multiple TickStack applications, you only need to install these DLL files once, as all our applications use the same files to connect to our license server.



The screenshot shows the 'MQL5 > Libraries' folder in the Metatrader terminal. The breadcrumb 'MQL5 > Libraries' is circled. Below it is a table of files:


Name	Date modified	Type	Size
 LicenseValidator_x64.dll	3/12/2025 8:14 AM	Application extension	22 KB
 LicenseValidator_x86.dll	3/12/2025 8:25 AM	Application extension	17 KB
 Myfxbook.dll	3/15/2025 5:50 PM	Application extension	16 KB

The first two rows of the table are circled.

Step 2: Allow DLL imports in your MT4/MT5 Terminal

From your Metatrader terminal, navigate to "Tools" -> "Options" and then click on the "Expert Advisors" tab. Then check the mark for "Allow DLL

Imports




Step 3: Install Application Files

- Copy the expert advisor (.ex5) or indicator file (.ex5) into the appropriate folder:
 1. Expert advisors go into the "Experts" folder
 2. Indicators go into the "Indicators" folder
- To locate these folders:
 1. Open your Metatrader terminal
 2. Click "File" → "Open Data Folder" in the top left corner
 3. Navigate to "MQL5" → "Experts" or "Indicators" as appropriate
- Restart your Metatrader Terminal
- Open the navigator and locate the application.
- Drag the application onto the chart you wish to use it on.



Step 4: Enable DLL imports in your Application (EA or Indicator)

- Under the Dependencies tab -> make sure to check the box to “Allow DLL imports”



Step 5: Activate Your Application

- When you run the application, you'll be prompted to enter your credentials in the application menu inputs
- Enter your email address and license key (*manage your license keys and associated accounts through our user portal:* <https://license.tickstack.io/portal/>)
- The program will run if all three conditions are valid: correct email, valid license key, and authorized account
- If any input is invalid, the program will terminate

Variable	Value
License Settings	
ab License Key	YOUR_LICENSE_KEY
ab User Email	youremail@email.com

Note: Each license allows usage on up to two accounts simultaneously. To change account numbers, manage your license keys through our user portal: <https://license.tickstack.io/portal/>

Your purchase confirmation email contains your portal password. If you own multiple TickStack products, you can manage all license keys from your personal dashboard.

For questions or technical support, please contact us at support@tickstack.io